

RENESAS TOOL NEWS on November 1, 2013: 131101/tn3

Further Lifting of Restrictions in Upgraded Revision of the QB-RL78G1C In-Circuit Emulator (IECUBE for the RL78/G1C Group of MCUs)

We announced the lifting of one restriction on the QB-RL78G1C in-circuit emulator in RENESAS TOOL NEWS issued on October 1, 2013. Note that the two restrictions listed in Section 2 were also lifted in the revision referred to on October 1.

Please go to the URL below to view the RENESAS TOOL NEWS issued on October 1, 2013.
<https://www.renesas.com/search/keyword-search.html#genre=document&q=131001tn2>

1. Product Concerned

QB-RL78G1C with revision control code A

To check to see your product's revision control code, follow these steps:

- (1) Start the self-diagnostic tool of the IECUBE to display the IEQBUTL dialog box.
- (2) Click START in the SELF-TEST tab of the dialog box.
- (3) In IECUBE Information of the SELF-TEST tab, look for the letter before "F/W" in such a representation as is shown below.

Example: IECUBE RL78.78K0R: **** A F/W: **. **

In this example, the revision control code is A.

2. Descriptions of Revision

The following restriction has been lifted:

- Supplying negative reference voltage to the A/D Converter (No. 2)
- The A/D conversion time when using 8 bit conversion mode (No. 3)

For details on these restrictions, see QB-RL78G1C Release Note.

This can be seen on the Web page from here.

3. Upgrading

Use CubeSuite+ V.2.01.00 or later.

To update yours, use either of the following methods:

Note: Those who have read the RENESAS TOOL NEWS of October 1, 2013 and updated CubeSuite+ do not need the update described below.

(1) Use Update Manager

On the Start menu, select Programs and then Renesas Electronics CubeSuite+ to start the Update Manager.

Note: If your CubeSuite+ has been launched with the rapid startup enabled, exit the CubeSuite+ once, and then run the Update Manager.

If the CubeSuite+ is resident in the notification area of Windows (system tray) due to rapid startup, an error occurs with the following message:

M0120001

Installation is suspended because "CubeSuite+W.exe" is running.

It will be resumed next time you start the tool.

(2) Download the installer of CubeSuite+ from:

https://www.renesas.com/cs+_download

Then install it.

[Disclaimer]

The past news contents have been based on information at the time of publication. Now changed or invalid information may be included. The URLs in the Tool News also may be subject to change or become invalid without prior notice.

© 2010-2016 Renesas Electronics Corporation. All rights reserved.